






Acrobat Distiller 7 _ PDF settings _ Imago/ts_16/01/06



1. You need the full version of Adobe Acrobat when converting PS files to PDFs via Distiller;
2. In Distiller 7 bring up the Press Quality settings which you then need to edit to match those shown here.
3. With the Press Quality settings showing as your default settings, go into Settings in the top tool bar: Settings > Edit Adobe PDF settings.
4. Click on each tab and edit to match these. Don't click on OK.
5. You can ignore the standards tab - it will show up saying none.
6. Once you have them all set, Save As and name your settings eg Press Quality_Imago/TS_110106
7. Then bring up this new setting as your default setting.
8. With this default chosen, drag & drop your PS files over Distiller.

NB. Your images and colours should all be in CMYK in your Quark file. Do not use Colour Management in Quark or Acrobat to convert your colours to CMYK.